


## MOVE-SOFTSTICK

*SOFTSTICK –  
simulated  
Joystick*

The buttons for movement provide three alternatives for switching the dialog of jog mode. The SOFTSTICK function represents a simulated joystick. The center point can be gripped by the mouse key and thus drawn in any kind of direction while moving the X and Y axes analogously to direction and displacement.




SOFTSTICK function for freely movable axis



Releasing the mouse key results in an immediate deceleration of the moving axis. Optionally there are 3 velocity graduations.

The circle enables moving XY and the right-hand bar allows moving the Z axes. By clicking the lock symbols one of the axis can be fixed and thus prevented from further movements.



Softstick – move with fixed Y-axes (Lock-Y)